



# Mobility and MANET


## Intelligent Transportation Systems

---

Rolland Vida


# Overview

- MANET – Mobile Ad Hoc Networks
- Meaning of „Ad Hoc”
  - Immediate, provisional, without preparation




# Ad hoc networks

- **No available infrastructure**
  - No internet connections, gateways, access points
  - No dedicated, deployed servers (AAA, DHCP, etc.), or services
- **No addressing based on IP subnets**
  - A problem for „classical” routing protocols
- **No reliable (stable) network devices**
  - Services provided by neighbors, fellow peer nodes
  - The status of my neighbor can change at any time – depleted battery, increased distance, etc.
  - I do not know my neighbors, I do not know if I can trust them
- **Self-organization**
  - Peer-to-peer paradigm (on the networking layer)
- **Multihop**
  - Communication (routing) over several hops (devices)



# MANET research topics

- Physical layer -> „*mobility models*”
  - Energy-efficient operation – adjusting radio power, sleep scheduling
  - Mobility-aware radio technologies
- **Data-link layer**
  - MAC (shared medium access, efficiency, decreasing the chance of collisions)
- **Networking layer**
  - Routing (dynamically changing topology, prefix-based routing not working)
- Upper layers
  - Packet retransmissions, TCP (packet loss, unreliable transmission medium)
  - Security (can be extended to any of the layers)
- Cross-layer optimization
  - The parallel optimization of several layers in the ISO/OSI model
  - Each layer might have its own influence over mobility




# Mobility types

- **Nomadic** mobility (nomadicity)
  - No communication while moving – device turned off
  - When restarting, new IP address, rebuilding the interrupted connections
- **Slow** mobility
  - E.g., people walking around in a building
  - University campus – students walking, biking
- **Fast** mobility
  - Cars, bikes, ...
- Moving networks...




# MANET vs. MONET

Edouard MANET



**M**obile **A**d Hoc **N**etwork

Claude MONET




**M**oving **N**etworks

- Networking devices moving together
  - E.g., passengers in a train, metro, bus, airplane
- Alternative name
  - **Networks in Motion – NEMO**

# NEMO – Networks in Motion

- Many MNs moving together
  - If they move together, let's handle their mobility together
- MR (mobile router) – default gateway
  - Provides the connection between NEMO-members and the outside world
  - Dedicated device, or one among the others assuming this role (periodic role changes)
    - Usually the biggest battery, the largest bandwidth, etc.
- The MNs have to register at the MR
  - They belong to the subnetwork of the MR
  - “Fixed” nodes in the network (relatively to the MR), their relative position does not change
    - Called also Fixed Local Nodes (FLN) because of that



# NEMO efficiency depends on the environment

- (Possible) drawbacks:

- Case of 100 MNs with 3G/4G mobile internet access in a city
- If the MNs do not join the NEMO
  - - personal mobility management needed for all the 100 MNs
  - + Any one of them receives the bandwidth provided by the given technology
- If all the MNs join the same NEMO
  - The MR link capacity becomes a bottleneck
  - In the worst case, the MNs receive only 1/100 of the bandwidth provided in the previous case


- (Possible) advantage:

- If 100 MNs on an airplane want to connect to the internet
  - The dedicated MR is the only node being able to connect
- Mobility management is optimal
  - Only the mobility of the MR has to be handled



# MANET routing

- Point-to-point
- Mobile node = end device + router






- **Who knows how to route?**

# Where to send the packet?


- **Sometimes only the source knows**

- All the route is stored in the header
  - Packet is routed based on the header
- **Source routing**, as the entire route is decided by the source
  - **E.g., Dynamic Source Routing (DSR)**
- Header can grow large
  - Fragmentation, low efficiency
  - Especially if long routes and not much data



- **Sometimes nobody knows**

- **Flooding** solutions
  - Everyone rebroadcasts the received packet
  - Hopefully it will reach the destination
- High burden on the wireless network, where resources are limited



# About routing in general

- Many routing protocols were developed
  - Some specific to MANETs
  - Some others adapted from the wired networks
- There is no one-size-fits-all protocol, which performs well in all circumstances
- Desired features for a MANET routing protocol
  - Distributed operation
  - Loop-free
  - Operation on demand
  - Security
  - Support for „sleeping” cycles
  - Support for one-directional links

# MANET routing

- **Proactive routing**

- The routing table is continuously maintained
  - No matter if there is traffic or not
- Relatively stable networks
- DSDV – based on the Bellman-Ford algorithm

- **On demand, reactive routing**

- Builds a route only if needed, if a packet has to be sent to the destination
- The routes are temporary, are dismantled if not used
- AODV

- **Hybrid protocols**

- Combining the previous two

- **Position-based protocols**

- Makes use of geographical position information for routing



# Constraints

- Delay
  - **Proactive** protocols provide lower delay, as routes are prepared in advance, and always up to date, ready to use
  - **Reactive** protocols provide large delay, as the route from A to B has to be found, when needed
- Overhead
  - **Proactive** protocols have a large overhead, too much signaling traffic to build and maintain the routes, even if no real data to send
  - **Reactive** protocols have lower overhead, useless routes are not maintained
- Each application will choose the best protocol
  - Low mobility -> **Proactive** protocols
  - High mobility -> **Reactive** protocols




# Ad Hoc On-Demand Distance Vector Routing (AODV)

- Reactive protocol
  - Maintains a routing table in each node, no need to store the route in the packet header
  - The route is built and maintained only if it is „active”


- To discover the route, the source broadcasts a **Route Request (RREQ)** message
- Those who receive it, rebroadcast it
- When a node rebroadcasts a Route Request message, it stores a **reverse path pointer** towards the node from where the request came
  - AODV symmetric (bi-directional) links
  - A small timer ensures that these records time out after a while
- If the RREQ arrives to the destination D, a **Route Reply (RREP)** message is sent back
- It will propagate along the path built from the reverse path pointers

# Route Request - AODV




**Node that already received a RREQ for D initiated by S**

# Route Request - AODV




# Route Requests - AODV



← Reverse Path pointer




# Reverse Path - AODV




- C receives a RREQ from neighbors (G and H)  
But does not rebroadcast it again

# Reverse Path - AODV




# Reverse Path - AODV




- node D does not forward anymore the RREQ message, as he is the destination

# Route Reply - AODV



 Path of the RREP message

## Forward Path - AODV




**As the RREP message travels from D to S, forward path pointers are stored in the intermediate nodes**



## Forward path pointer



# Data sending - AODV



For sending the useful data, these forward path pointers are used

The path is not included in the header

# Timers

- The **reverse path records** are deleted after a while from the routing tables
  - We should take into account the specificities of the wireless domain and the size of the network, leave time for the RREP message to propagate back before deleting the record
- The forward path pointer is deleted if it becomes inactive – no traffic
  - *active\_route\_timeout*
  - If no traffic, the record is deleted, even if the path is still valid